

Content of List Logical Disk Drive Properties.ps1 (Site 1)

```
$strComputer = "."
$collItems = get-wmiobject -class "Win32_LogicalDisk" -namespace "root\CIMV2" `
-computername $strComputer
foreach ($objItem in $collItems) {
  write-host "Access: " $objItem.Access
  write-host "Availability: " $objItem.Availability
  write-host "Block Size: " $objItem.BlockSize
  write-host "Caption: " $objItem.Caption
  write-host "Compressed: " $objItem.Compressed
  write-host "Configuration Manager Error Code: " $objItem.ConfigManagerErrorCode
  write-host "Configuration Manager User Configuration: " $objItem.ConfigManagerUserConfig
  write-host "Creation Class Name: " $objItem.CreationClassName
  write-host "Description: " $objItem.Description
  write-host "Device ID: " $objItem.DeviceID
  write-host "Drive Type: " $objItem.DriveType
  write-host "Error Cleared: " $objItem.ErrorCleared
  write-host "Error Description: " $objItem.ErrorDescription
  write-host "Error Methodology: " $objItem.ErrorMethodology
  write-host "File System: " $objItem.FileSystem
  write-host "Free Space: " $objItem.FreeSpace
  write-host "Installation Date: " $objItem.InstallDate
  write-host "Last Error Code: " $objItem.LastErrorCode
  write-host "Maximum Component Length: " $objItem.MaximumComponentLength
  write-host "Media Type: " $objItem.MediaType
  write-host "Name: " $objItem.Name
  write-host "Number Of Blocks: " $objItem.NumberOfBlocks
  write-host "PNP Device ID: " $objItem.PNPDeviceID
  write-host "Power Management Capabilities: " $objItem.PowerManagementCapabilities
  write-host "Power Management Supported: " $objItem.PowerManagementSupported
  write-host "Provider Name: " $objItem.ProviderName
  write-host "Purpose: " $objItem.Purpose
  write-host "Quotas Disabled: " $objItem.QuotasDisabled
  write-host "Quotas Incomplete: " $objItem.QuotasIncomplete
  write-host "Quotas Rebuilding: " $objItem.QuotasRebuilding
  write-host "Size: " $objItem.Size
  write-host "Status: " $objItem.Status
  write-host "Status Information: " $objItem.StatusInfo
  write-host "Supports Disk Quotas: " $objItem.SupportsDiskQuotas
  write-host "Supports File-Based Compression: " $objItem.SupportsFileBasedCompression
  write-host "System Creation Class Name: " $objItem.SystemCreationClassName
  write-host "System Name: " $objItem.SystemName
  write-host "Volume Dirty: " $objItem.VolumeDirty
  write-host "Volume Name: " $objItem.VolumeName
  write-host "Volume Serial Number: " $objItem.VolumeSerialNumber
  write-host
}
}
```