

## Content of List Processor Information.ps1 ( Site 1 )

```
$strComputer = "."
$collItems = get-wmiobject -class "Win32_Processor" -namespace "root\CIMV2" `
-computername $strComputer
foreach ($objItem in $collItems) {
  write-host "Address Width: " $objItem.AddressWidth
  write-host "Architecture: " $objItem.Architecture
  write-host "Availability: " $objItem.Availability
  write-host "Caption: " $objItem.Caption
  write-host "Configuration Manager Error Code: " $objItem.ConfigManagerErrorCode
  write-host "Configuration Manager User Configuration: " $objItem.ConfigManagerUserConfig
  write-host "CPU Status: " $objItem.CpuStatus
  write-host "Creation Class Name: " $objItem.CreationClassName
  write-host "Current Clock Speed: " $objItem.CurrentClockSpeed
  write-host "Current Voltage: " $objItem.CurrentVoltage
  write-host "Data Width: " $objItem.DataWidth
  write-host "Description: " $objItem.Description
  write-host "Device ID: " $objItem.DeviceID
  write-host "Error Cleared: " $objItem.ErrorCleared
  write-host "Error Description: " $objItem.ErrorDescription
  write-host "Ext Clock: " $objItem.ExtClock
  write-host "Family: " $objItem.Family
  write-host "Installation Date: " $objItem.InstallDate
  write-host "L2 Cache Size: " $objItem.L2CacheSize
  write-host "L2 Cache Speed: " $objItem.L2CacheSpeed
  write-host "Last Error Code: " $objItem.LastErrorCode
  write-host "Level: " $objItem.Level
  write-host "Load Percentage: " $objItem.LoadPercentage
  write-host "Manufacturer: " $objItem.Manufacturer
  write-host "Maximum Clock Speed: " $objItem.MaxClockSpeed
  write-host "Name: " $objItem.Name
  write-host "Other Family Description: " $objItem.OtherFamilyDescription
  write-host "PNP Device ID: " $objItem.PNPDeviceID
  write-host "Power Management Capabilities: " $objItem.PowerManagementCapabilities
  write-host "Power Management Supported: " $objItem.PowerManagementSupported
  write-host "Processor ID: " $objItem.ProcessorId
  write-host "Processor Type: " $objItem.ProcessorType
  write-host "Revision: " $objItem.Revision
  write-host "Role: " $objItem.Role
  write-host "Socket Designation: " $objItem.SocketDesignation
  write-host "Status: " $objItem.Status
  write-host "Status Information: " $objItem.StatusInfo
  write-host "Stepping: " $objItem.Stepping
  write-host "System Creation Class Name: " $objItem.SystemCreationClassName
  write-host "System Name: " $objItem.SystemName
  write-host "Unique ID: " $objItem.UniqueId
  write-host "Upgrade Method: " $objItem.UpgradeMethod
  write-host "Version: " $objItem.Version
  write-host "Voltage Caps: " $objItem.VoltageCaps
  write-host
}
}
```