

Content of WMI CIM_PhysicalExtent Query.vbs (Site 1)

```
On Error Resume Next
strComputer = "."
Set objWMIService = GetObject("winmgmts:\\" & strComputer & "\root\cimv2")
Set colItems = objWMIService.ExecQuery("Select * from CIM_PhysicalExtent",48)
For Each objItem in colItems
  Wscript.Echo "Access: " & objItem.Access
  Wscript.Echo "Availability: " & objItem.Availability
  Wscript.Echo "BlockSize: " & objItem.BlockSize
  Wscript.Echo "Caption: " & objItem.Caption
  Wscript.Echo "ConfigManagerErrorCode: " & objItem.ConfigManagerErrorCode
  Wscript.Echo "ConfigManagerUserConfig: " & objItem.ConfigManagerUserConfig
  Wscript.Echo "CreationClassName: " & objItem.CreationClassName
  Wscript.Echo "Description: " & objItem.Description
  Wscript.Echo "DeviceID: " & objItem.DeviceID
  Wscript.Echo "ErrorCleared: " & objItem.ErrorCleared
  Wscript.Echo "ErrorDescription: " & objItem.ErrorDescription
  Wscript.Echo "ErrorMethodology: " & objItem.ErrorMethodology
  Wscript.Echo "InstallDate: " & objItem.InstallDate
  Wscript.Echo "LastErrorCode: " & objItem.LastErrorCode
  Wscript.Echo "Name: " & objItem.Name
  Wscript.Echo "NumberOfBlocks: " & objItem.NumberOfBlocks
  Wscript.Echo "PNPDeviceID: " & objItem.PNPDeviceID
  Wscript.Echo "PowerManagementCapabilities: " & objItem.PowerManagementCapabilities
  Wscript.Echo "PowerManagementSupported: " & objItem.PowerManagementSupported
  Wscript.Echo "Purpose: " & objItem.Purpose
  Wscript.Echo "Status: " & objItem.Status
  Wscript.Echo "StatusInfo: " & objItem.StatusInfo
  Wscript.Echo "SystemCreationClassName: " & objItem.SystemCreationClassName
  Wscript.Echo "SystemName: " & objItem.SystemName
  Wscript.Echo "UnitsBeforeCheckDataInterleave: " & objItem.UnitsBeforeCheckDataInterleave
  Wscript.Echo "UnitsOfCheckData: " & objItem.UnitsOfCheckData
  Wscript.Echo "UnitsOfUserData: " & objItem.UnitsOfUserData
Next
```