

## Content of WMI Win32\_Publisher11SelectedTable Query.vbs ( Site 1 )

On Error Resume Next

```
Const wbemFlagReturnImmediately = &h10
Const wbemFlagForwardOnly = &h20
```

```
arrComputers = Array("")
```

```
For Each strComputer In arrComputers
```

```
WScript.Echo
```

```
WScript.Echo "=====
```

```
WScript.Echo "Computer: " & strComputer
```

```
WScript.Echo "=====
```

```
Set objWMIService = GetObject("winmgmts:\\" & strComputer & "\root\MSAPPS11")
```

```
Set collItems = objWMIService.ExecQuery("SELECT * FROM Win32_Publisher11SelectedTable", "WQL", _
wbemFlagReturnImmediately + wbemFlagForwardOnly)
```

```
For Each objItem In collItems
```

```
WScript.Echo "AllowAutoFit: " & objItem.AllowAutoFit
```

```
WScript.Echo "AllowPageBreaks: " & objItem.AllowPageBreaks
```

```
WScript.Echo "BottomMargin: " & objItem.BottomMargin
```

```
WScript.Echo "CellsAllowAutoFit: " & objItem.CellsAllowAutoFit
```

```
WScript.Echo "Columns: " & objItem.Columns
```

```
WScript.Echo "LeftIndent: " & objItem.LeftIndent
```

```
WScript.Echo "LeftMargin: " & objItem.LeftMargin
```

```
WScript.Echo "NestingLevel: " & objItem.NestingLevel
```

```
WScript.Echo "Page: " & objItem.Page
```

```
WScript.Echo "PreferredWidth: " & objItem.PreferredWidth
```

```
WScript.Echo "PreferredWidthType: " & objItem.PreferredWidthType
```

```
WScript.Echo "RightMargin: " & objItem.RightMargin
```

```
WScript.Echo "RowAlignment: " & objItem.RowAlignment
```

```
WScript.Echo "RowHeightRule: " & objItem.RowHeightRule
```

```
WScript.Echo "Rows: " & objItem.Rows
```

```
WScript.Echo "RowsAllowPageBreaks: " & objItem.RowsAllowPageBreaks
```

```
WScript.Echo "Section: " & objItem.Section
```

```
WScript.Echo "Spacing: " & objItem.Spacing
```

```
WScript.Echo "Tables: " & objItem.Tables
```

```
WScript.Echo "TopMargin: " & objItem.TopMargin
```

```
WScript.Echo "Uniform: " & objItem.Uniform
```

```
WScript.Echo
```

```
Next
```

```
Next
```