

## Content of List Cache Memory Information.ps1 ( Site 1 )

```
$strComputer = "."
$collItems = get-wmiobject -class "Win32_CacheMemory" -namespace "root\CIMV2" `
-computername $strComputer
foreach ($objItem in $collItems) {
  write-host "Access: " $objItem.Access
  write-host "Additional Error Data: " $objItem.AdditionalErrorData
  write-host "Associativity: " $objItem.Associativity
  write-host "Availability: " $objItem.Availability
  write-host "Block Size: " $objItem.BlockSize
  write-host "Cache Speed: " $objItem.CacheSpeed
  write-host "Cache Type: " $objItem.CacheType
  write-host "Caption: " $objItem.Caption
  write-host "Configuration Manager Error Code: " $objItem.ConfigManagerErrorCode
  write-host "Configuration Manager User Configuration: " $objItem.ConfigManagerUserConfig
  write-host "Correctable Error: " $objItem.CorrectableError
  write-host "Creation Class Name: " $objItem.CreationClassName
  write-host "Current SRAM: " $objItem.CurrentSRAM
  write-host "Description: " $objItem.Description
  write-host "Device ID: " $objItem.DeviceID
  write-host "Ending Address: " $objItem.EndingAddress
  write-host "Error Access: " $objItem.ErrorAccess
  write-host "Error Address: " $objItem.ErrorAddress
  write-host "Error Cleared: " $objItem.ErrorCleared
  write-host "Error Correct Type: " $objItem.ErrorCorrectType
  write-host "Error Data: " $objItem.ErrorData
  write-host "Error Data Order: " $objItem.ErrorDataOrder
  write-host "Error Description: " $objItem.ErrorDescription
  write-host "Error Information: " $objItem.ErrorInfo
  write-host "Error Methodology: " $objItem.ErrorMethodology
  write-host "Error Resolution: " $objItem.ErrorResolution
  write-host "Error Time: " $objItem.ErrorTime
  write-host "Error Transfer Size: " $objItem.ErrorTransferSize
  write-host "Flush Timer: " $objItem.FlushTimer
  write-host "Installation Date: " $objItem.InstallDate
  write-host "Installed Size: " $objItem.InstalledSize
  write-host "Last Error Code: " $objItem.LastErrorCode
  write-host "Level: " $objItem.Level
  write-host "Line Size: " $objItem.LineSize
  write-host "Location: " $objItem.Location
  write-host "Maximum Cache Size: " $objItem.MaxCacheSize
  write-host "Name: " $objItem.Name
  write-host "Number Of Blocks: " $objItem.NumberOfBlocks
  write-host "Other Error Description: " $objItem.OtherErrorDescription
  write-host "PNP Device ID: " $objItem.PNPDeviceID
  write-host "Power Management Capabilities: " $objItem.PowerManagementCapabilities
  write-host "Power Management Supported: " $objItem.PowerManagementSupported
  write-host "Purpose: " $objItem.Purpose
  write-host "Read Policy: " $objItem.ReadPolicy
  write-host "Replacement Policy: " $objItem.ReplacementPolicy
  write-host "Starting Address: " $objItem.StartingAddress
  write-host "Status: " $objItem.Status
  write-host "Status Information: " $objItem.StatusInfo
  write-host "Supported SRAM: " $objItem.SupportedSRAM
  write-host "System Creation Class Name: " $objItem.SystemCreationClassName
  write-host "System-Level Address: " $objItem.SystemLevelAddress
  write-host "System Name: " $objItem.SystemName
  write-host "Write Policy: " $objItem.WritePolicy
  write-host
}
}
```