

Content of List Memory Array Information.ps1 (Site 1)

```
$strComputer = "."
$collItems = get-wmiobject -class "Win32_MemoryArray" -namespace "root\CIMV2" `
-computername $strComputer
foreach ($objItem in $collItems) {
  write-host "Access: " $objItem.Access
  write-host "Additional Error Data: " $objItem.AdditionalErrorData
  write-host "Availability: " $objItem.Availability
  write-host "Block Size: " $objItem.BlockSize
  write-host "Caption: " $objItem.Caption
  write-host "Configuration Manager Error Code: " $objItem.ConfigManagerErrorCode
  write-host "Configuration Manager User Configuration: " $objItem.ConfigManagerUserConfig
  write-host "Correctable Error: " $objItem.CorrectableError
  write-host "Creation Class Name: " $objItem.CreationClassName
  write-host "Description: " $objItem.Description
  write-host "Device ID: " $objItem.DeviceID
  write-host "Ending Address: " $objItem.EndingAddress
  write-host "Error Access: " $objItem.ErrorAccess
  write-host "Error Address: " $objItem.ErrorAddress
  write-host "Error Cleared: " $objItem.ErrorCleared
  write-host "Error Data: " $objItem.ErrorData
  write-host "Error Data Order: " $objItem.ErrorDataOrder
  write-host "Error Description: " $objItem.ErrorDescription
  write-host "Error Granularity: " $objItem.ErrorGranularity
  write-host "Error Information: " $objItem.ErrorInfo
  write-host "Error Methodology: " $objItem.ErrorMethodology
  write-host "Error Resolution: " $objItem.ErrorResolution
  write-host "Error Time: " $objItem.ErrorTime
  write-host "Error Transfer Size: " $objItem.ErrorTransferSize
  write-host "Installation Date: " $objItem.InstallDate
  write-host "Last Error Code: " $objItem.LastErrorCode
  write-host "Name: " $objItem.Name
  write-host "Number Of Blocks: " $objItem.NumberOfBlocks
  write-host "Other Error Description: " $objItem.OtherErrorDescription
  write-host "PNP Device ID: " $objItem.PNPDeviceID
  write-host "Power Management Capabilities: " $objItem.PowerManagementCapabilities
  write-host "Power Management Supported: " $objItem.PowerManagementSupported
  write-host "Purpose: " $objItem.Purpose
  write-host "Starting Address: " $objItem.StartingAddress
  write-host "Status: " $objItem.Status
  write-host "Status Information: " $objItem.StatusInfo
  write-host "System Creation Class Name: " $objItem.SystemCreationClassName
  write-host "System-Level Address: " $objItem.SystemLevelAddress
  write-host "System Name: " $objItem.SystemName
  write-host
}
}
```