

Content of List Physical Disk Properties.ps1 (Site 1)

```
$strComputer = "."
$collItems = get-wmiobject -class "Win32_DiskDrive" -namespace "root\CIMV2" `
-computername $strComputer
foreach ($objItem in $collItems) {
  write-host "Availability: " $objItem.Availability
  write-host "Bytes Per Sector: " $objItem.BytesPerSector
  write-host "Capabilities: " $objItem.Capabilities
  write-host "Capability Descriptions: " $objItem.CapabilityDescriptions
  write-host "Caption: " $objItem.Caption
  write-host "Compression Method: " $objItem.CompressionMethod
  write-host "Configuration Manager Error Code: " $objItem.ConfigManagerErrorCode
  write-host "Configuration Manager User Configuration: " $objItem.ConfigManagerUserConfig
  write-host "Creation Class Name: " $objItem.CreationClassName
  write-host "Default Block Size: " $objItem.DefaultBlockSize
  write-host "Description: " $objItem.Description
  write-host "Device ID: " $objItem.DeviceID
  write-host "Error Cleared: " $objItem.ErrorCleared
  write-host "Error Description: " $objItem.ErrorDescription
  write-host "Error Methodology: " $objItem.ErrorMethodology
  write-host "Index: " $objItem.Index
  write-host "Installation Date: " $objItem.InstallDate
  write-host "Interface Type: " $objItem.InterfaceType
  write-host "Last Error Code: " $objItem.LastErrorCode
  write-host "Manufacturer: " $objItem.Manufacturer
  write-host "Maximum Block Size: " $objItem.MaxBlockSize
  write-host "Maximum Media Size: " $objItem.MaxMediaSize
  write-host "Media Loaded: " $objItem.MediaLoaded
  write-host "Media Type: " $objItem.MediaType
  write-host "Minimum Block Size: " $objItem.MinBlockSize
  write-host "Model: " $objItem.Model
  write-host "Name: " $objItem.Name
  write-host "Needs Cleaning: " $objItem.NeedsCleaning
  write-host "Number Of Media Supported: " $objItem.NumberOfMediaSupported
  write-host "Partitions: " $objItem.Partitions
  write-host "PNP Device ID: " $objItem.PNPDeviceID
  write-host "Power Management Capabilities: " $objItem.PowerManagementCapabilities
  write-host "Power Management Supported: " $objItem.PowerManagementSupported
  write-host "SCSI Bus: " $objItem.SCSIBus
  write-host "SCSI Logical Unit: " $objItem.SCSILogicalUnit
  write-host "SCSI Port: " $objItem.SCSIPort
  write-host "SCSI Target ID: " $objItem.SCSITargetId
  write-host "Sectors Per Track: " $objItem.SectorsPerTrack
  write-host "Signature: " $objItem.Signature
  write-host "Size: " $objItem.Size
  write-host "Status: " $objItem.Status
  write-host "Status Information: " $objItem.StatusInfo
  write-host "System Creation Class Name: " $objItem.SystemCreationClassName
  write-host "System Name: " $objItem.SystemName
  write-host "Total Cylinders: " $objItem.TotalCylinders
  write-host "Total Heads: " $objItem.TotalHeads
  write-host "Total Sectors: " $objItem.TotalSectors
  write-host "Total Tracks: " $objItem.TotalTracks
  write-host "Tracks Per Cylinder: " $objItem.TracksPerCylinder
  write-host
}
```