

Content of WMI Win32_PerfFormattedData_AspNet_114322_AspNetv114322 Query.js (Site 1)

```
var wbemFlagReturnImmediately = 0x10;
var wbemFlagForwardOnly = 0x20;

var arrComputers = new Array(".");
for (i = 0; i < arrComputers.length; i++) {
    WScript.Echo();
    WScript.Echo("=====");
    WScript.Echo("Computer: " + arrComputers[i]);
    WScript.Echo("=====");

var objWMIService = GetObject("winmgmts:\\" + arrComputers[i] + "\root\cimv2");
var colItems = objWMIService.ExecQuery("SELECT * FROM Win32_PerfFormattedData_AspNet_114322_AspNetv114322", "WQL",
    wbemFlagReturnImmediately | wbemFlagForwardOnly);

var enumItems = new Enumerator(colItems);
for (; !enumItems.atEnd(); enumItems.moveNext()) {
    var objItem = enumItems.item();

    WScript.Echo("ApplicationRestarts: " + objItem.ApplicationRestarts);
    WScript.Echo("ApplicationsRunning: " + objItem.ApplicationsRunning);
    WScript.Echo("Caption: " + objItem.Caption);
    WScript.Echo("Description: " + objItem.Description);
    WScript.Echo("Frequency_Object: " + objItem.Frequency_Object);
    WScript.Echo("Frequency_PerfTime: " + objItem.Frequency_PerfTime);
    WScript.Echo("Frequency_Sys100NS: " + objItem.Frequency_Sys100NS);
    WScript.Echo("Name: " + objItem.Name);
    WScript.Echo("RequestExecutionTime: " + objItem.RequestExecutionTime);
    WScript.Echo("RequestsCurrent: " + objItem.RequestsCurrent);
    WScript.Echo("RequestsDisconnected: " + objItem.RequestsDisconnected);
    WScript.Echo("RequestsQueued: " + objItem.RequestsQueued);
    WScript.Echo("RequestsRejected: " + objItem.RequestsRejected);
    WScript.Echo("RequestWaitTime: " + objItem.RequestWaitTime);
    WScript.Echo("StateServerSessionsAbandoned: " + objItem.StateServerSessionsAbandoned);
    WScript.Echo("StateServerSessionsActive: " + objItem.StateServerSessionsActive);
    WScript.Echo("StateServerSessionsTimedOut: " + objItem.StateServerSessionsTimedOut);
    WScript.Echo("StateServerSessionsTotal: " + objItem.StateServerSessionsTotal);
    WScript.Echo("Timestamp_Object: " + objItem.Timestamp_Object);
    WScript.Echo("Timestamp_PerfTime: " + objItem.Timestamp_PerfTime);
    WScript.Echo("Timestamp_Sys100NS: " + objItem.Timestamp_Sys100NS);
    WScript.Echo("WorkerProcessesRunning: " + objItem.WorkerProcessesRunning);
    WScript.Echo("WorkerProcessRestarts: " + objItem.WorkerProcessRestarts);
}

}
```