

Content of WMI Win32_PerfFormattedData_PerfOS_Memory Query.js (Site 1)

```
var wbemFlagReturnImmediately = 0x10;
var wbemFlagForwardOnly = 0x20;

var arrComputers = new Array("");
for (i = 0; i < arrComputers.length; i++) {
    WScript.Echo();
    WScript.Echo("=====");
    WScript.Echo("Computer: " + arrComputers[i]);
    WScript.Echo("=====");

    var objWMIService = GetObject("winmgmts:\\\\" + arrComputers[i] + "\\root\\CIMV2");
    var collItems = objWMIService.ExecQuery("SELECT * FROM Win32_PerfFormattedData_PerfOS_Memory", "WQL",
        wbemFlagReturnImmediately | wbemFlagForwardOnly);

    var enumItems = new Enumerator(collItems);
    for (; !enumItems.atEnd(); enumItems.moveNext()) {
        var objItem = enumItems.item();

        WScript.Echo("AvailableBytes: " + objItem.AvailableBytes);
        WScript.Echo("AvailableKBytes: " + objItem.AvailableKBytes);
        WScript.Echo("AvailableMBytes: " + objItem.AvailableMBytes);
        WScript.Echo("CacheBytes: " + objItem.CacheBytes);
        WScript.Echo("CacheBytesPeak: " + objItem.CacheBytesPeak);
        WScript.Echo("CacheFaultsPerSec: " + objItem.CacheFaultsPerSec);
        WScript.Echo("Caption: " + objItem.Caption);
        WScript.Echo("CommitLimit: " + objItem.CommitLimit);
        WScript.Echo("CommittedBytes: " + objItem.CommittedBytes);
        WScript.Echo("DemandZeroFaultsPerSec: " + objItem.DemandZeroFaultsPerSec);
        WScript.Echo("Description: " + objItem.Description);
        WScript.Echo("FreeSystemPageTableEntries: " + objItem.FreeSystemPageTableEntries);
        WScript.Echo("Frequency_Object: " + objItem.Frequency_Object);
        WScript.Echo("Frequency_PerfTime: " + objItem.Frequency_PerfTime);
        WScript.Echo("Frequency_Sys100NS: " + objItem.Frequency_Sys100NS);
        WScript.Echo("Name: " + objItem.Name);
        WScript.Echo("PageFaultsPerSec: " + objItem.PageFaultsPerSec);
        WScript.Echo("PageReadsPerSec: " + objItem.PageReadsPerSec);
        WScript.Echo("PagesInputPerSec: " + objItem.PagesInputPerSec);
        WScript.Echo("PagesOutputPerSec: " + objItem.PagesOutputPerSec);
        WScript.Echo("PagesPerSec: " + objItem.PagesPerSec);
        WScript.Echo("PageWritesPerSec: " + objItem.PageWritesPerSec);
        WScript.Echo("PercentCommittedBytesInUse: " + objItem.PercentCommittedBytesInUse);
        WScript.Echo("PoolNonpagedAllocs: " + objItem.PoolNonpagedAllocs);
        WScript.Echo("PoolNonpagedBytes: " + objItem.PoolNonpagedBytes);
        WScript.Echo("PoolPagedAllocs: " + objItem.PoolPagedAllocs);
        WScript.Echo("PoolPagedBytes: " + objItem.PoolPagedBytes);
        WScript.Echo("PoolPagedResidentBytes: " + objItem.PoolPagedResidentBytes);
        WScript.Echo("SystemCacheResidentBytes: " + objItem.SystemCacheResidentBytes);
        WScript.Echo("SystemCodeResidentBytes: " + objItem.SystemCodeResidentBytes);
        WScript.Echo("SystemCodeTotalBytes: " + objItem.SystemCodeTotalBytes);
        WScript.Echo("SystemDriverResidentBytes: " + objItem.SystemDriverResidentBytes);
        WScript.Echo("SystemDriverTotalBytes: " + objItem.SystemDriverTotalBytes);
        WScript.Echo("Timestamp_Object: " + objItem.Timestamp_Object);
        WScript.Echo("Timestamp_PerfTime: " + objItem.Timestamp_PerfTime);
        WScript.Echo("Timestamp_Sys100NS: " + objItem.Timestamp_Sys100NS);
        WScript.Echo("TransitionFaultsPerSec: " + objItem.TransitionFaultsPerSec);
        WScript.Echo("WriteCopiesPerSec: " + objItem.WriteCopiesPerSec);
    }
}
```